

AP XPRESS

8 OZ PER ACRE

AP XPRESS IS A 7-12-1 WITH 12% HUMIC ACID AND PLANT GROWTH REGULATORS. HUMIC ACID ENHANCES NUTRIENT AVAILABILITY AND UPTAKE, WHILE GROWTH HORMONES WORK TOGETHER TO STIMULATE ROOT AND SHOOT DEVELOPMENT.

KEY BENEFITS

- SUPPORTS STRONG EARLY ROOT DEVELOPMENT
- PROMOTES UNIFORM EMERGENCE AND EARLY VIGOR
- PROVIDES READILY AVAILABLE PHOSPHORUS FOR EARLY ENERGY TRANSFER
- FLEXIBLE PLACEMENT OPTIONS FOR STARTER OR FOLIAR PROGRAMS
- DESIGNED TO FIT SEAMLESSLY INTO EXISTING FERTILITY PROGRAMS

STORAGE & HANDLING

- STORE IN A COOL, DRY LOCATION
- KEEP CONTAINER TIGHTLY CLOSED
- DO NOT REUSE EMPTY CONTAINERS
- TRIPLE RINSE CONTAINERS AND DISPOSE OF ACCORDING TO LOCAL, STATE, AND FEDERAL REGULATIONS

APPLICATION RATES

- IN-FURROW: 4-6 OZ PER ACRE
 - FOLIAR: 4-8 OZ PER ACRE AT PEAK PRODUCTIVE STAGE
- ALWAYS FOLLOW SAFE FERTILIZER PLACEMENT PRACTICES TO AVOID CROP INJURY.

Harvey's
SEEDING PROGRESS SINCE 1871

AP PRODUCTS

MANUFACTURED FOR:
HARVEY FERTILIZER & GAS COMPANY
1291 US HIGHWAY 258 N
KINSTON, NC 28504
(252) 522-0698
WWW.HARVEYFERTILIZERANDGAS.COM

GUARANTEED ANALYSIS

- TOTAL NITROGEN (N) 7.0%
 - 7.0% UREA NITROGEN
- AVAILABLE PHOSPHATE (P₂O₅) 12.0%
- SOLUBLE POTASH (K₂O) 1.0%

DERIVED FROM UREA, AMMONIUM PHOSPHATE, AND POTASSIUM CARBONATE.

RECOMMENDED CROPS

- CORN
 - IN-FURROW AT PLANTING, FOLIARLY AT V3 - V6
- COTTON
 - IN-FURROW AT PLANTING, FOLIARLY AT 4TH TRUE LEAF, PIN HEAD SQUARE, & EARLY BLOOM
- PEANUTS
 - 3RD TRUE LEAF, INITIAL PEG, & EARLY POD FILL
- SOYBEANS
 - IN-FURROW AT PLANTING, FOLIARLY V3 - V6
- WHEAT
 - FOLIARLY BEHIND GRAIN DRILL, 4-6 WEEKS AFTER PLANTING
- TOBACCO
 - 5 - 8 LEAF STAGE
- SWEET POTATOES
 - 28 DAYS AFTER TRANSPLANTING, 42 DAYS AFTER TRANSPLANTING
- CUCURBITS
 - 14 DAYS AFTER TRANSPLANTING, 28 DAYS AFTER TRANSPLANTING
- PEPPER
 - 28 DAYS AFTER TRANSPLANTING, 42 DAYS AFTER TRANSPLANTING
- TOMATO
 - 28 DAYS AFTER TRANSPLANTING, 42 DAYS AFTER TRANSPLANTING
- STRAWBERRY
 - EVERY TWO WEEKS AFTER DORMANCY BREAK, FIRST VIABLE BLOOM